



620 Applegate St. Philomath, OR 97370 • 541-929-5650 • fax 541-929-5277

ECO Meter Firmware Update

The version 3.01 and newer firmware installed in ECO meters improves functionality in several ways.

- The meter's serial number, "Ser" in ECOView host software, is displayed at the top of the meter's settings.
- For those meters equipped with memory, the new firmware allows the existing memory to be allocated more efficiently, resulting in improved data storage capacity.
- The Reference column is still unused, but now reflects the emission wavelength of the fluorescence signal (695 nm) and the scattering wavelength of the scattering signal. See the meter-specific user's guide for sample outputs.

Date (MM/DD/YY)	Time (HH:MM:SS)	N/U (λ)	Chl Sig (counts)	Therm
6/14/2005	7:57:55	695	75	16380
6/14/2005	7:57:56	695	76	16380
6/14/2005	7:57:57	695	75	16380
6/14/2005	7:57:58	695	74	16380

Sample fluorometer output

Date (MM/DD/YY)	Time (HH:MM:SS)	N/U (λ)	BB Sig (counts)	N/U (Therm)
8/22/06	9:57:55	532	72	564
8/22/06	9:57:56	532	71	564
8/22/06	9:57:57	532	71	564
8/22/06	9:57:58	532	71	564

Sample scattering meter output