


X+ FAQ

How to install X+?.....	1
How to install the license key?.....	1
How to change the logo in HTML reports?	1
How to change the location of the reports folder?.....	1

How to install X+?

1. Download the X+ installer from https://www.gmccs.de/downloads_x+.php
2. Close Mastercam
3. Run the X+ installer as administrator
4. Restart Mastercam
5. Optional: Create a X+ ribbon menu bar



How to install the license key?

1. If not already done, rename the license file to **license.xml**
2. Copy it to: "C:\Users\Public\Documents\X+\license.xml"

How to change the logo in HTML reports?

1. Replace **%public%\documents\X+\logo.png** with your own logo.png.

How to change the location of the reports folder?

The default reports folder is located at **%public%\documents\X+\reports**.

With a symbolic link we can change the location.

1. Rename the default folder. I.e.: **%public%\documents\X+\reports_old**
2. Create a new folder. I.e.: **z:\my reports**
3. Run Windows command prompt as administrator.
4. Use **mklink** to create your symbolic link.

```
c:\windows\system32>mklink /D "C:\Users\Public\Documents\X+\reports" "z:\my reports"
```

```
C:\WINDOWS\system32>mklink /D "C:\Users\Public\Documents\X+\reports" "z:\my reports"
symbolische Verknüpfung erstellt für C:\Users\Public\Documents\X+\reports <==> z:\my reports
C:\WINDOWS\system32>
```